
HOME THEORY Page 1 of 4

Print this page

Objective: We will configure Routers 1, 2, and 4 with IP addresses and ping between them to test connectivity.



Configuring IP Addresses:

- 1. First you want to connect to router one and assign a hostname of eRouter1 eRouter1(config)#
- 2. What mode must you be in to set the IP address on an interface?

eRouter1(config-if)#

3. What command will set the IP address on the Ethernet 0 interface to 10.1.1.1 255.255.255.0?

eRouter1(config-if)#ip address 10.1.1.1 255.255.255.0 🗸

4. Now you need to enable the interface. What command did you use?

HOME THEORY Page 2 of 4

eRouter1(config-if)#no shutdown 🗸
5. Now set the IP address on the S0 interface of eRouter1 to 172.16.10.1 255.255.255.0
eRouter1(config-if)#no shut
6. Next click on the button eRouter2 at the top of your screen.
7. Assign a hostname of eRouter2.
Router(config)#hostname eRouter2 🗸
8. Set the IP address for the Ethernet 0 interface to 10.1.1.2 255.255.255.0
eRouter2(config-if)#ip address 10.1.1.2 255.255.255.0 🗸
9. Enable the interface.
eRouter2(config-if)#no shutdown
10. Now click on the button eRouter4 at the top of your screen.
11. Assign an Hostname of eRouter4 and an IP address of 172.16.10.2 255.255.255.0 on the serial 0 interface.
eRouter4(config-if)#ip address 172.16.10.2 255.255.255.0 🗸
12. Make sure you enable the interface.
eRouter4(config-if)#no shutdown 🗸
13. Connect back to eRouter1
14. Try and ping eRouter2's Ethernet interface
eRouter1#ping 10.1.1.2
15. Try and ping eRouter4's Serial 0 interface.
eRouter1#ping 172.16.10.2
16. What command will let you verify that your interfaces line state and protocol state are up?
eRouter#show ip interface brief
17. View your running configuration and verify that the IP addresses appear.
eRouter#show running-config
18. View detailed IP information about each interface.

HOME THEORY Page 3 of 4

eRouter#show ip interface	~
---------------------------	---

IP ADDRESSES LAB

This is equivalent to the lab above with the exception that it does not give you the answers as you complete each step.

- 1. First you want to connect to router one assign a hostname of eRouter1. What command did you use? Selectionar Router1: enable || conf t || hostname eRouter1
- 2. What mode must you be in to set the IP address on an interface? eRouter1 (config-if)#
- 3. What command will set the IP address on the Ethernet 0 interface to 10.1.1.1 255.255.255.0? ip address 10.1.1.1 255.255.255.0
- 4. Now you need to enable the interface. What command did you use? no shutdown
- 5. Now set the IP address on the S0 interface of eRouter1 to 172.16.10.1 255.255.255.0? What command will do this? interface serial0 || ip address 172.16.10.1 255.255.255.0 || no shutdown
- 6. Next click on the button eRouter2 at the top of your screen.
- 7. Assign a hostname of eRouter2. What command did you use? hostname eRouter2
- 8. Set the IP address for the Ethernet 0 interface to 10.1.1.2 255.255.255.0. What command did you use? interface ethernet0 || ip address 10.1.1.2 255.255.255.0
- 9. Enable the interface. What command does this? no shutdown
- 10. Now click on the button eRouter4 at the top of your screen.
- 11. Assign an IP address of 172.16.10.2 255.255.255.0 on the serial 0 interface. What command did you use? ip address 172.16.10.2 255.255.255.0
- 12. Make sure you enable the interface. What command did you use? no shutdown
- 13. Connect back to eRouter1
- 14. Try and ping eRouter2's Ethernet interface What command allows you to ping? ping 10.1.1.2
- **15.** Try and ping eRouter4's Serial 0 interface. What address is the Serial 0 interface? ping 172.16.10.2
- **16.** What command will let you verify that your interfaces are up and up? show ip interface brief
- 17. View your running configuration and verify that the IP addresses appear. What command allows you to view your running-configuration? <u>show running-configuration</u>

HOME THEORY Page 4 of 4

18. View detailed IP information about each interface. What command will do this?

show ip interface

Copyright (c) 1998-2003 Boson Software, Inc. All Rights Reserved.